

CADClick: Setup VISI direct insertion driver and plugin for versions from 2017 (all 64-bit)

1. Download & install the latest CADClick interface update:

[Download CADClick interfaces update](#)

2. Download & install of the VISI-Plugins

[Download VISI plugin](#)

3. Set up menu entry for each desired compatible VISI version

The menu entry in the VISI-specific file „ext3d.mnu“ must be extended as follows using a text editor.

To do this, add the following lines to the file

"<VISI-installation>\User_Profiles\Default\Eng\ext3d.mnu" hinzu.

```
"Meusburger"  
{  
  "CADClick® Plugin", "DLL ccPlugin_VISI.exec 1";  
};
```

If you are using a different language or specific environment, you will find the file in the appropriate subdirectory of „<VISI-installation>\User_Profiles“

4. CAD export from the Meusburger offline shop

4.1. Compile parts list and start CAD transfer

4.2. Select the desired VISI version at „direct insert“

4.2.1. Optional: The settings button can be used to switch on the definable alignment/rotation in CAD

4.2.2. Start export by clicking on the arrow

4.2.3. A message appears that the VISI plugin has been detected

IMPORTANT: LEAVE THIS MESSAGE UNTOUCHED - DO NOT PRESS A BUTTON!

4.3. Via the menu „Meusburger --> CADClick® Plugin“ set up in VISI you can import the CAD data

4.3.1. Select insertion point --> model is inserted

4.3.2. Optional: Define alignment/rotation of the imported model